
MCC HAT Library Documentation

Release 0.4.0

Measurement Computing

Jun 14, 2018

CONTENTS

| | | |
|----------|-----------------------------------------|-----------|
| 1 | Hardware Overview | 1 |
| 1.1 | MCC 118 | 1 |
| 1.1.1 | Board components | 2 |
| 1.1.1.1 | Screw terminals | 2 |
| 1.1.1.2 | Address jumpers | 2 |
| 1.1.1.3 | Status LED | 3 |
| 1.1.1.4 | Header connector | 3 |
| 1.1.2 | Functional block diagram | 3 |
| 1.1.3 | Functional details | 3 |
| 1.1.3.1 | Clock mode | 3 |
| 1.1.4 | Specifications | 4 |
| 1.2 | MCC 134 | 9 |
| 1.2.1 | Board components | 10 |
| 1.2.1.1 | Screw terminals | 10 |
| 1.2.1.2 | Status LED | 10 |
| 1.2.1.3 | Header connector | 10 |
| 1.3 | MCC 152 | 10 |
| 1.3.1 | Board components | 11 |
| 1.3.1.1 | Screw terminals | 11 |
| 1.3.1.2 | Status LED | 11 |
| 1.3.1.3 | Header connector | 11 |
| 2 | Installing the HAT board | 13 |
| 2.1 | Installing a single board | 13 |
| 2.2 | Installing multiple boards | 14 |
| 3 | Installing and Using the Library | 15 |
| 3.1 | Installation | 15 |
| 3.2 | Creating a C program | 16 |
| 3.3 | Creating a Python program | 16 |
| 4 | C Library Reference | 17 |
| 4.1 | Global functions and data | 17 |
| 4.1.1 | Functions | 17 |
| 4.1.2 | Data types and definitions | 18 |
| 4.1.2.1 | HAT IDs | 18 |
| 4.1.2.2 | Result Codes | 19 |
| 4.1.2.3 | HatInfo structure | 19 |
| 4.1.2.4 | Analog Input / Scan Options | 19 |
| 4.2 | MCC 118 functions and data | 20 |

| | | |
|--------------|--------------------------------------|-----------|
| 4.2.1 | Functions | 20 |
| 4.2.2 | Data definitions | 26 |
| 4.2.2.1 | Trigger Modes | 26 |
| 4.2.2.2 | Scan Status Flags | 26 |
| 4.3 | MCC 134 functions and data | 26 |
| 4.3.1 | Functions | 26 |
| 4.3.2 | Data definitions | 30 |
| 4.3.2.1 | Thermocouple Types | 30 |
| 4.4 | MCC 152 functions and data | 31 |
| 4.4.1 | Functions | 31 |
| 4.4.2 | Data definitions | 39 |
| 5 | Python Library Reference | 41 |
| 5.1 | Global methods and data | 41 |
| 5.1.1 | Methods | 41 |
| 5.1.2 | Data | 42 |
| 5.1.2.1 | Hat IDs | 42 |
| 5.1.2.2 | Trigger modes | 42 |
| 5.1.3 | HatError class | 42 |
| 5.2 | MCC 118 class | 42 |
| 5.2.1 | Methods | 42 |
| 5.3 | MCC 134 class | 48 |
| 5.3.1 | Methods | 48 |
| 5.3.2 | Data | 52 |
| 5.3.2.1 | Thermocouple types | 52 |
| Index | | 53 |

HARDWARE OVERVIEW

The MCC HATs are Raspberry Pi add-on boards (Hardware Attached on Top). They adhere to the Raspberry Pi HAT specification, but also extend it to allow stacking up to 8 MCC boards on a single Raspberry Pi.


We provide Python and C libraries, documentation, and examples to allow you to develop your own applications using our boards.

1.1 MCC 118

The MCC 118 is an 8-channel analog voltage input board with the following features:

- 12-bit, 100 kS/s A/D converter
- ± 10 V single-ended analog inputs
- Factory calibration with ± 20.8 mV input accuracy
- Hardware sample I/O clock
- Onboard sample buffers
- Digital trigger input

MCC 118



1.1.1 Board components

1.1.1.1 Screw terminals

- **CH 0 In to CH 7 In:** Single-ended analog input terminals.
- **Clock:** Bidirectional terminal for pacer I/O. Set the direction with software. Set for input to pace operations with an external clock signal, or output to pace operations with the internal sample clock.
- **Trigger:** External digital trigger input terminal. The trigger mode is software configurable for edge or level sensitive, rising or falling edge, high or low level.
- **AGND:** Common ground for the analog input terminals.
- **DGND:** Common ground for the clock and trigger terminals.

1.1.1.2 Address jumpers

- **A0 to A2:** Used to identify each HAT when multiple boards are connected. The first HAT connected to the Raspberry Pi must be at address 0 (no jumper). Install a jumper on each additional connected board. Refer to the *Installing multiple boards* discussion for more information about the recommended addressing method.


1.1.1.3 Status LED

The LED turns on when the board is connected to a Raspberry Pi with external power applied. You can flash the LED with software.

1.1.1.4 Header connector

The board header is used to connect with the Raspberry Pi. Refer to *Installing the HAT board* for more information about the header connector.


1.1.2 Functional block diagram



1.1.3 Functional details

1.1.3.1 Clock mode

The clock input / output on the MCC 118 is used to output the internal sample clock or apply an external sample clock to the device. Each pulse on the clock initiates a series of conversions of the selected channels in the scan. For example, when scanning channels 0, 1, and 2 the conversion activity will be:



1.1.4 Specifications

All specifications are subject to change without notice.

Typical for 25 °C unless otherwise specified.

Specifications in *italic text* are guaranteed by design.

Analog input

Table 1. General analog input specifications

| Parameter | Conditions | Specification |
|---------------------------------------|---------------------------------|---------------------------------------------------------------------------------------------------------------------------------------|
| A/D converter type | | Successive approximation |
| ADC resolution | | 12 bits |
| Number of channels | | 8 single-ended |
| Input voltage range | | ± 10 V |
| <i>Absolute maximum input voltage</i> | <i>CHx relative to AGND</i> | <ul style="list-style-type: none"> ± 25 V max (power on) ± 25 V max (power off) |
| <i>Input impedance</i> | | <ul style="list-style-type: none"> 1 MΩ (power on) 1 MΩ (power off) |
| <i>Input bias current</i> | 10 V input | –12 μ A |
| | 0 V input | 2 μ A |
| | –10 V input | 12 μ A |
| <i>Monotonicity</i> | | Guaranteed |
| Input bandwidth | Small signal (–3 dB) | 150 kHz |
| Maximum working voltage | Input range relative to AGND | ± 10.1 V max |
| Crosstalk | Adjacent channels, DC to 10 kHz | –75 dB |
| Input coupling | | DC |
| Recommended warm-up time | | 1 minute min |
| Sampling rate, hardware paced | Internal pacer | 0.004 S/s to 100 kS/s, software-selectable |
| | External pacer | 100 kS/s max |
| Sampling mode | | One A/D conversion for each configured channel per clock |
| Conversion time | Per channel | 8 μ s |
| Sample clock source | | <ul style="list-style-type: none"> Internal sample clock External sample clock input on terminal CLK |
| Channel queue | | Up to eight unique, ascending channels |
| Throughput, Raspberry Pi® 2 / 3 | Single board | 100 kS/s max |
| | Multiple boards | Up to 320 kS/s aggregate (Note 1) |
| Throughput, Raspberry Pi A+ / B+ | Single board | Up to 100 kS/s (Note 1) |
| | Multiple boards | Up to 100 kS/s aggregate (Note 1) |

Note 1: Depends on the load on the Raspberry Pi processor. The highest throughput may be achieved by using a Raspberry Pi 3.

Accuracy

Analog input DC voltage measurement accuracy

Table 2. DC Accuracy components and specifications. All values are (\pm)

| Range | Gain error (% of reading) | Offset error (mV) | Absolute accuracy at Full Scale (mV) | Gain temperature coefficient (% reading/ $^{\circ}$ C) | Offset temperature coefficient (mV/ $^{\circ}$ C) |
|------------|------------------------------|----------------------|--------------------------------------------|--------------------------------------------------------------|------------------------------------------------------------|
| ± 10 V | 0.098 | 11 | 20.8 | 0.016 | 0.87 |

Noise performance

For the peak to peak noise distribution test, the input channel is connected to AGND at the input terminal block, and 12,000 samples are acquired at the maximum throughput.

Table 3. Noise performance specifications

| Range | Counts | LSB _{rms} |
|------------|--------|--------------------|
| ± 10 V | 5 | 0.76 |

External digital trigger

Table 4. External digital trigger specifications

| Parameter | Specification |
|------------------------------|-----------------------------------------------------------------------------------------------|
| Trigger source | TRIG input |
| Trigger mode | Software configurable for edge or level sensitive, rising or falling edge, high or low level. |
| Trigger latency | Internal pacer: 1 μ s max External pacer: 1 μ s + 1 pacer clock cycle max |
| Trigger pulse width | 125 ns min |
| Input type | Schmitt trigger, weak pull-down to ground (approximately 10 K) |
| Input high voltage threshold | 2.64 V min |
| Input low voltage threshold | 0.66 V max |
| Input voltage limits | 5.5 V absolute max -0.5 V absolute min 0 V recommended min |

External sample clock input/output

Table 5. External sample clock I/O specifications

| Parameter | Specification |
|---------------------------------|------------------------------------------------------------------------------------------------------------------------------------------|
| Terminal name | CLK |
| Terminal types | Bidirectional, defaults to input when not sampling analog channels |
| Direction (software-selectable) | Output: Outputs internal sample clock; active on rising edge Input: Receives sample clock from external source; active on rising edge |
| Input clock rate | 100 kHz max |
| Input clock pulse width | 400 ns min |
| Input type | Schmitt trigger, weak pull-down to ground in input mode (approximately 10 K), protected with 150 Ω series resistor |
| Input high voltage threshold | 2.64 V min |
| Input low voltage threshold | 0.66 V max |
| Input voltage limits | 5.5V absolute max -0.5V absolute min 0V recommended min |
| Output high voltage | 3.0 V min (IOH = -50 μ A) 2.65 V min (IOH = -3 mA) |
| Output low voltage | 0.1 V max (IOL = 50 μ A) 0.8 V max (IOL = 3 mA) |
| Output current | \pm 3 mA max |

Memory

Table 6. Memory specifications

| Parameter | Specification |
|---------------------|--------------------------------------------------------------|
| Data FIFO | 7 K (7,168) analog input samples |
| Non-volatile memory | 4 KB (ID and calibration storage, no user-modifiable memory) |

Power

Table 7. Power specifications

| Parameter | Conditions | Specification |
|-----------------------------|------------|---------------|
| Supply current, 3.3V supply | Typical | 35 mA |
| | Maximum | 55 mA |

Interface specifications

Table 8. Interface specifications

| Parameter | Specification |
|-------------------------------------------|----------------------------------------------------------------------------------------------------------------------------|
| Raspberry Pi TM GPIO pins used | GPIO 8, GPIO 9, GPIO 10, GPIO 11 (SPI interface) ID_SD, ID_SC (ID EEPROM) GPIO 12, GPIO 13, GPIO 26, (Board address) |
| Data interface type | SPI slave device, CE0 chip select |
| SPI mode | 1 |
| SPI clock rate | 10 MHz, max |

Environmental

Table 9. Environmental specifications

| Parameter | Specification |
|-----------------------------|--------------------------|
| Operating temperature range | 0 °C to 55 °C |
| Storage temperature range | –40 °C to 85 °C |
| Humidity | 0% to 90% non-condensing |

Mechanical

Table 10. Mechanical specifications

| Parameter | Specification |
|------------------------|------------------------------------------------|
| Dimensions (L × W × H) | 65 × 56.5 × 12 mm (2.56 × 2.22 × 0.47 in.) max |

Screw terminal connector

Table 11. Screw terminal connector specifications

| Parameter | Specification |
|------------------|------------------|
| Connector type | Screw terminal |
| Wire gauge range | 16 AWG to 30 AWG |

Table 12. Screw terminal pinout

| Connector J2 | | |
|--------------|-------------|-----------------------------|
| Pin | Signal name | Pin description |
| 1 | CH0 | Channel 0 |
| 2 | CH1 | Channel 1 |
| 3 | GND | Analog ground |
| 4 | CH2 | Channel 2 |
| 5 | CH3 | Channel 3 |
| 6 | GND | Analog ground |
| Connector J3 | | |
| Pin | Signal name | Pin description |
| 7 | CH4 | Channel 4 |
| 8 | CH5 | Channel 5 |
| 9 | GND | Analog ground |
| 10 | CH6 | Channel 6 |
| 11 | CH7 | Channel 7 |
| 12 | GND | Analog ground |
| 13 | CLK | Sample clock input / output |
| 14 | GND | Digital ground |
| 15 | TRIG | Digital trigger input |
| 16 | GND | Digital ground |


1.2 MCC 134

4-channel thermocouple input board

- 24-bit A/D converter
- Onboard 16-bit temperature sensor for cold junction compensation
- Linearization for J, K, R, S, T, N, E, B type thermocouples
- Open thermocouple detection
- Thermocouple inputs are electrically isolated from the Raspberry Pi for use in harsh environments

MCC 134

Status LED -



- A2
- A1
- A0

| | | | | | | | |
|----|----|----|----|----|----|----|----|
| + | - | + | - | + | - | + | - |
| 0 | 0 | 1 | 1 | 2 | 2 | 3 | 3 |
| Ch | Ch | Ch | Ch | Ch | Ch | Ch | Ch |

1.2.1 Board components

1.2.1.1 Screw terminals

- **CH 0 In** to **CH 3 In**: Differential thermocouple input terminals.

1.2.1.2 Status LED

The LED turns on when the board is connected to a Raspberry Pi with external power applied.


1.2.1.3 Header connector

The board header is used to connect with the Raspberry Pi. Refer to *Installing the HAT board* for more information about the header connector.

1.3 MCC 152

2-channel analog output / 8 digital I/O board

- 12-bit D/A converter
- 0 - 5V output
- 5V / 3.3V selectable digital I/O
- Programmable pull-up/pull-down resistors
- 25mA sink per output
- Interrupt on input change



1.3.1 Board components

1.3.1.1 Screw terminals

- **A00** to **A01**: Analog output terminals.
- **DIO0** to **DIO7**: Digital input/output terminals

1.3.1.2 Status LED

The LED turns on when the board is connected to a Raspberry Pi with external power applied.

1.3.1.3 Header connector

The board header is used to connect with the Raspberry Pi. Refer to *Installing the HAT board* for more information about the header connector.


INSTALLING THE HAT BOARD

2.1 Installing a single board

1. Power off the Raspberry Pi.
2. Locate the 4 standoffs. A typical standoff is shown here:



3. Attach the 4 standoffs to the Raspberry Pi by inserting the male threaded portion through the 4 corner holes on the Raspberry Pi from the top and securing them with the included nuts from the bottom.
4. Install the 2x20 receptacle with extended leads onto the Raspberry Pi GPIO header by pressing the female portion of the receptacle onto the header pins, being careful not to bend the leads of the receptacle. The 2x20 receptacle looks like:



5. **The HAT must be at address 0.** Remove any jumpers from the address header locations A0-A2 on the HAT board.
6. Insert the HAT board onto the leads of the 2x20 receptacle so that the leads go into the holes on the bottom of the HAT board and come out through the 2x20 connector on the top of the HAT board. The 4 mounting holes in the corners of the HAT board must line up with the standoffs. Slide the HAT board down until it rests on the standoffs.
7. Insert the included screws through the mounting holes on the HAT board into the threaded holes in the standoffs and lightly tighten them.

2.2 Installing multiple boards

1. Follow steps 1-6 in the single board installation procedure for the first HAT board.
2. Connect all desired field wiring to the first board because the screw terminals will not be accessible once additional boards are installed above it.
3. Install the standoffs of the additional board by inserting the male threaded portions through the 4 corner holes of the installed HAT board and threading them into the standoffs below.
4. Install the next 2x20 receptacle with extended leads onto the leads of the previous 2x20 receptacle by pressing the female portion of the new receptacle onto the previous receptacle leads, being careful not to bend the leads of either receptacle.
5. Install the appropriate address jumpers onto address header locations A0-A2 of the new HAT board. The recommended addressing method is to have the addresses increment from 0 as the boards are installed, i.e. 0, 1, 2, and so forth. **There must always be a board at address 0.** The jumpers are installed in this manner (install jumpers where “Y” appears):

| Address | A0 | A1 | A2 |
|---------|----|----|----|
| 0 | | | |
| 1 | Y | | |
| 2 | | Y | |
| 3 | Y | Y | |
| 4 | | | Y |
| 5 | Y | | Y |
| 6 | | Y | Y |
| 7 | Y | Y | Y |

6. Insert the new HAT board onto the leads of the 2x20 receptacle so that the leads go into the holes on the bottom of the HAT board and come out through the 2x20 connector on the top of the HAT board. The 4 mounting holes in the corners of the HAT board must line up with the standoffs. Slide the HAT board down until it rests on the standoffs.
7. Repeat steps 2-6 for each board to be added.
8. Insert the included screws through the mounting holes on the top HAT board into the threaded holes in the standoffs and lightly tighten them.

INSTALLING AND USING THE LIBRARY

The project is hosted at <https://github.com/nwright98/daqhats>.

3.1 Installation

1. Power off the Raspberry Pi then attach one or more HAT boards, using unique address settings for each. When using a single board, leave it at address 0 (all address jumpers removed.) One board must always be at address 0 so the OS reads a HAT EEPROM and initializes the hardware correctly.
2. Power on the Pi and log in. Open a terminal window if using the graphical interface.
3. If git is not already installed, update installation packages and install it:

```
sudo apt-get update
sudo apt-get install git
```

4. Download this package to your user folder with git:

```
cd ~
git clone https://github.com/nwright98/daqhats
```

5. Build and install the shared library and optional Python support. The installer will ask if you want to install Python 2 and Python 3 support. It will also detect the HAT board EEPROMs and save the contents if needed:

```
cd ~/daqhats
sudo ./install.sh
```

6. [Optional] To update the firmware on your MCC 118 board(s) use the firmware update tool. The “0” in the example below is the board address. The line with the “-b” option updates the bootloader. Repeat the two commands for each MCC 118 address in your board stack:

```
mcc118_firmware_update -b 0 ~/daqhats/tools/MCC_118.hex
mcc118_firmware_update 0 ~/daqhats/tools/MCC_118.hex
```

You can now run the example programs under ~/daqhats/examples and create your own programs.

To uninstall the package use:

```
cd ~/daqhats
sudo ./uninstall.sh
```

If you change your board stackup and have more than one HAT board attached you must update the saved EEPROM images for the library to have the correct board information:

```
sudo daqhats_read_eeproms
```

3.2 Creating a C program

- The daqhats headers are installed in `/usr/local/include/daqhats`. Add the compiler option `-I/usr/local/include` in order to find the header files when compiling, and the include line `#include <daqhats/daqhats.h>` to your source code.
- The shared library, `libdaqhats.so`, is installed in `/usr/local/lib`. Add the linker option `-ldaqhats` to include this library.
- Study the example programs, example makefile, and library documentation for more information.

3.3 Creating a Python program

- The Python package is named *daqhats*. Use it in your code with `import daqhats`.
- Study the example programs and library documentation for more information.

C LIBRARY REFERENCE

The C library is organized as a global function for listing the HAT boards attached to your system, and board-specific functions to provide full functionality for each type of board. The library may be used with C and C++.

4.1 Global functions and data

4.1.1 Functions

| Function | Description |
|---------------------------------------|-------------------------------------------|
| <code>hat_list()</code> | Return a list of detected MCC HAT boards. |
| <code>hat_wait_for_interrupt()</code> | Wait for an interrupt to occur. |
| <code>hat_interrupt_active()</code> | Read the current interrupt status. |

int **hat_list** (uint16_t *filter_id*, struct *HatInfo* * *list*)

Return a list of detected MCC HAT boards.

It creates the list from the HAT EEPROM files that are currently on the system. In the case of a single HAT at address 0 this information is automatically provided by Raspbian. However, when you have a stack of multiple boards you must extract the EEPROM images using the `daqhats_read_eeproms` tool.

Example usage:

```
int count = hat_list(HAT_ID_ANY, NULL);

if (count > 0)
{
    struct HatInfo* list = (struct HatInfo*)malloc(count * sizeof(struct
↪HatInfo));
    hat_list(HAT_ID_ANY, list);

    // perform actions with list

    free(list);
}
```

Return The number of boards found.

Parameters

- `filter_id`: An optional *ID* filter to only return boards with a specific ID. Use *HAT_ID_ANY* to return all boards.

- `list`: A pointer to a user-allocated array of struct *HatInfo*. The function will fill the structures with information about the detected boards. You may have an array of the maximum number of boards (*MAX_NUMBER_HATS*) or call this function while passing NULL for `list`, which will return the count of boards found, then allocate the correct amount of memory and call this function again with a valid pointer.

int **hat_wait_for_interrupt** (int *timeout*)

Wait for an interrupt to occur.

It waits for the interrupt signal to become active, with a timeout parameter.

Return RESULT_TIMEOUT, RESULT_SUCCESS, or RESULT_UNDEFINED.

Parameters

- `timeout`: Wait timeout in milliseconds. -1 to wait forever, 0 to return immediately.

int **hat_interrupt_active** (void)

Read the current interrupt status.

It returns the status of the interrupt signal. This signal can be shared by multiple boards so the status of each board that may generate must be read and the interrupt source(s) cleared before the interrupt will become inactive.

Return 1 if interrupt is active, 0 if inactive.

4.1.2 Data types and definitions

MAX_NUMBER_HATS 8

The maximum number of MCC HATs that may be connected.

4.1.2.1 HAT IDs

enum HatIDs

Known MCC HAT IDs.

Values:

HAT_ID_ANY = 0

Match any MCC ID in *hat_list()*.

HAT_ID_MCC_118 = 0x0142

MCC 118 ID.

HAT_ID_MCC_118_BOOTLOADER = 0x8142

MCC 118 in firmware update mode ID.

HAT_ID_MCC_134 = 0x0143

MCC 134 ID.

HAT_ID_MCC_152 = 0x0144

MCC 152 ID.

4.1.2.2 Result Codes

enum ResultCode

Return values from the library functions.

Values:

RESULT_SUCCESS = 0

Success, no errors.

RESULT_BAD_PARAMETER = -1

A parameter passed to the function was incorrect.

RESULT_BUSY = -2

The device is busy.

RESULT_TIMEOUT = -3

There was a timeout accessing a resource.

RESULT_LOCK_TIMEOUT = -4

There was a timeout while obtaining a resource lock.

RESULT_INVALID_DEVICE = -5

The device at the specified address is not the correct type.

RESULT_RESOURCE_UNAVAIL = -6

A needed resource was not available.

RESULT_UNDEFINED = -10

Some other error occurred.

4.1.2.3 HatInfo structure

struct HatInfo

Contains information about a specific board.

Public Members

uint8_t address

The board address.

uint16_t id

The product ID, one of *HatIDs*.

uint16_t version

The hardware version.

char HatInfo::product_name[256]

The product name.

4.1.2.4 Analog Input / Scan Options

OPTS_NOSCALEDATA (0x0001)

Read or write ADC/DAC code instead of scaled data (voltage, temperature, etc.)

OPTS_NOCALIBRATEDATA (0x0002)

Read or write uncalibrated data.

OPTS_EXTCLOCK (0x0004)

Use an external sample clock.

OPTS_EXTTRIGGER (0x0008)

Use an external trigger.

OPTS_CONTINUOUS (0x0010)

Scan until stopped.

4.2 MCC 118 functions and data

4.2.1 Functions

| Function | Description |
|-----------------------------------------------------|-----------------------------------------------------------|
| <code>mcc118_open()</code> | Open an MCC 118 for use. |
| <code>mcc118_is_open()</code> | Check if an MCC 118 is open. |
| <code>mcc118_close()</code> | Close an MCC 118. |
| <code>mcc118_blink_led()</code> | Blink the MCC 118 LED. |
| <code>mcc118_firmware_version()</code> | Get the firmware version. |
| <code>mcc118_serial()</code> | Read the serial number. |
| <code>mcc118_calibration_date()</code> | Read the calibration date. |
| <code>mcc118_calibration_coefficient_read()</code> | Read the calibration coefficients for a channel. |
| <code>mcc118_calibration_coefficient_write()</code> | Write the calibration coefficients for a channel. |
| <code>mcc118_a_in_num_channels()</code> | Get the number of analog input channels. |
| <code>mcc118_a_in_read()</code> | Read an analog input value. |
| <code>mcc118_trigger_mode()</code> | Set the external trigger input mode. |
| <code>mcc118_a_in_scan_actual_rate()</code> | Read the actual sample rate for a set of scan parameters. |
| <code>mcc118_a_in_scan_start()</code> | Start a hardware-paced analog input scan. |
| <code>mcc118_a_in_scan_buffer_size()</code> | Read the size of the internal scan data buffer. |
| <code>mcc118_a_in_scan_read()</code> | Read scan data / status. |
| <code>mcc118_a_in_scan_channel_count()</code> | Get the number of channels in the current scan. |
| <code>mcc118_a_in_scan_stop()</code> | Stop the scan. |
| <code>mcc118_a_in_scan_cleanup()</code> | Free scan resources. |

int **mcc118_open** (uint8_t *address*)

Open a connection to the MCC 118 device at the specified address.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7).

int **mcc118_close** (uint8_t *address*)

Close a connection to an MCC 118 device and free allocated resources.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7).

int **mcc118_is_open** (uint8_t *address*)

Check if an MCC 118 is open.

Return 1 if open, 0 if not open.

Parameters

- *address*: The board address (0 - 7).

int **mcc118_blink_led** (uint8_t *address*, uint8_t *count*)

Blink the LED on the MCC 118.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7).
- *count*: The number of times to blink (0 - 255).

int **mcc118_firmware_version** (uint8_t *address*, uint16_t * *version*, uint16_t * *boot_version*)

Return the board firmware and bootloader versions.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7). Board must already be opened.
- *version*: Receives the firmware version. The version will be in BCD hexadecimal with the high byte as the major version and low byte as minor, i.e. 0x0103 is version 1.03.
- *boot_version*: Receives the bootloader version. The version will be in BCD hexadecimal as above.

int **mcc118_serial** (uint8_t *address*, char * *buffer*)

Read the MCC 118 serial number.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7). Board must already be opened.
- *buffer*: Pass a user-allocated buffer pointer to receive the serial number as a string. The buffer must be at least 9 characters in length.

int **mcc118_calibration_date** (uint8_t *address*, char * *buffer*)

Read the MCC 118 calibration date.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7). Board must already be opened.
- *buffer*: Pass a user-allocated buffer pointer to receive the date as a string (format “YYYY-MM-DD”). The buffer must be at least 11 characters in length.

int **mcc118_calibration_coefficient_read** (uint8_t *address*, uint8_t *channel*, double * *slope*, double * *offset*)

Read the MCC 118 calibration coefficients for a single channel.

The coefficients are applied in the library as:

$$\text{calibrated_ADC_code} = (\text{raw_ADC_code} * \text{slope}) + \text{offset}$$

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7). Board must already be opened.
- *channel*: The channel number (0 - 7).
- *slope*: Receives the slope.
- *offset*: Receives the offset.

int **mcc118_calibration_coefficient_write** (uint8_t *address*, uint8_t *channel*, double *slope*, double *offset*)

Temporarily write the MCC 118 calibration coefficients for a single channel.

The user can apply their own calibration coefficients by writing to these values. The values will reset to the factory values from the EEPROM whenever *mcc118_open()* is called. This function will fail and return *RESULT_BUSY* if a scan is running when it is called.

The coefficients are applied in the library as:

$$\text{calibrated_ADC_code} = (\text{raw_ADC_code} * \text{slope}) + \text{offset}$$

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7). Board must already be opened.
- *channel*: The channel number (0 - 7).
- *slope*: The new slope value.
- *offset*: The new offset value.

int **mcc118_a_in_num_channels** (void)

Return the number of analog input channels on the MCC 118.

Return The number of channels.

int **mcc118_a_in_read** (uint8_t *address*, uint8_t *channel*, uint32_t *options*, double * *value*)

Perform a single reading of an analog input channel and return the value.

Will return *RESULT_BUSY* if called while a scan is running.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7). Board must already be opened.
- *channel*: The analog input channel number, 0 - 7.

- `options`: Options bitmask (only `OPTS_NOSCALEDATA` and `OPTS_NOCALIBRATEDATA` are supported)
- `value`: Receives the analog input value.

int `mcc118_trigger_mode` (uint8_t *address*, uint8_t *mode*)

Set the trigger input mode.

Return *Result code*, `RESULT_SUCCESS` if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `mode`: One of the *trigger mode* values.

int `mcc118_a_in_scan_actual_rate` (uint8_t *channel_count*, double *sample_rate_per_channel*, double * *actual_sample_rate_per_channel*)

Read the actual sample rate per channel for a requested sample rate.

The internal scan clock is generated from a 16 MHz clock source so only discrete frequency steps can be achieved. This function will return the actual rate for a requested channel count, rate and burst mode setting. This function does not perform any actions with a board, it simply calculates the rate.

Return *Result code*, `RESULT_SUCCESS` if successful, `RESULT_BAD_PARAMETER` if the scan parameters are not achievable on an MCC 118.

Parameters

- `channel_count`: The number of channels in the scan.
- `sample_rate_per_channel`: The desired sampling rate in samples per second per channel, max 100,000.
- `actual_sample_rate_per_channel`: The actual sample rate that would occur when requesting this rate on an MCC 118, or 0 if there is an error.

int `mcc118_a_in_scan_start` (uint8_t *address*, uint8_t *channel_mask*, uint32_t *samples_per_channel*, double *sample_rate_per_channel*, uint32_t *options*)

Start a hardware-paced analog input scan.

The scan runs as a separate thread from the user's code. The function will allocate a scan buffer and read data from the device into that buffer. The user reads the data from this buffer and the scan status using the `mcc118_a_in_scan_read()` function. `mcc118_a_in_scan_stop()` is used to stop a continuous scan, or to stop a finite scan before it completes. The user must call `mcc118_a_in_scan_cleanup()` after the scan has finished and all desired data has been read; this frees all resources from the scan and allows additional scans to be performed.

The buffer size will be allocated as follows:

Finite mode: Total number of samples in the scan

Continuous mode (buffer size is per channel): Either `samples_per_channel` or the value in the following table, whichever is greater

| Sample Rate | Buffer Size (per channel) |
|---------------|---------------------------|
| Not specified | 10 kS |
| 0-100 S/s | 1 kS |
| 100-10k S/s | 10 kS |
| 10k-100k S/s | 100 kS |

Specifying a very large value for `samples_per_channel` could use too much of the Raspberry Pi memory. If the memory allocation fails, the function will return `RESULT_RESOURCE_UNAVAIL`. The allocation could succeed, but the lack of free memory could cause other problems in the Raspberry Pi. If you need to acquire a high number of samples then it is better to run the scan in continuous mode and stop it when you have acquired the desired amount of data. If a scan is already running this function will return `RESULT_BUSY`.

Return *Result code*, `RESULT_SUCCESS` if successful, `RESULT_BUSY` if a scan is already running.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel_mask`: A bit mask of the channels to be scanned. Set each bit to enable the associated channel (0x01 - 0xFF.)
- `samples_per_channel`: The number of samples to acquire for each channel in the scan.
- `sample_rate_per_channel`: The sampling rate in samples per second per channel, max 100,000. When using an external sample clock set this value to the maximum expected rate of the clock.
- `options`: The options for the scan. This is a bitmask and may be an ORed combination of:
 - `OPTS_NOSCALEDATA`: Return ADC codes instead of voltage.
 - `OPTS_NOCALIBRATEDATA`: Return uncalibrated values.
 - `OPTS_EXTCLOCK`: Use an external sample clock on the CLK input.
 - `OPTS_EXTTRIGGER`: Use an external trigger source on the TRIG input.
 - `OPTS_CONTINUOUS`: Scan until stopped (`samples_per_channel` is only used for buffer allocation.)

int `mcc118_a_in_scan_buffer_size` (uint8_t *address*, uint32_t * *buffer_size_samples*)

Returns the size of the internal scan data buffer.

An internal data buffer is allocated for the scan when `mcc118_a_in_scan_start()` is called. This function returns the total size of that buffer in samples.

Return *Result code*, `RESULT_SUCCESS` if successful, `RESULT_RESOURCE_UNAVAIL` if a scan is not currently running under this instance of the device, or `RESULT_BAD_PARAMETER` if the address is invalid or `buffer_size_samples` is NULL.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `buffer_size_samples`: Receives the size of the buffer in samples. Each sample is a **double**.

int `mcc118_a_in_scan_read` (uint8_t *address*, uint16_t * *status*, int32_t *samples_per_channel*, double *timeout*, double * *buffer*, uint32_t *buffer_size_samples*, uint32_t * *samples_read_per_channel*)

Reads status and multiple samples from an analog input scan.

The scan is started with `mcc118_a_in_scan_start()` and runs in a background thread that reads the data from the board into an internal scan buffer. This function reads the data from the scan buffer, and returns the current scan status.

Return *Result code*, `RESULT_SUCCESS` if successful, `RESULT_RESOURCE_UNAVAIL` if a scan is not currently running under this instance of the device.

Parameters

- **address**: The board address (0 - 7). Board must already be opened.
- **status**: Receives the scan status, an ORed combination of the following flags:
 - *STATUS_HW_OVERRUN*: The device scan buffer was not read fast enough and data was lost.
 - *STATUS_BUFFER_OVERRUN*: The thread scan buffer was not read by the user fast enough and data was lost.
 - *STATUS_TRIGGERED*: The trigger conditions have been met.
 - *STATUS_RUNNING*: The scan is running.
- **samples_per_channel**: The number of samples per channel to read. Specify **-1** to read all available samples, or **0** to only read the scan status and not return data. If buffer does not contain enough space then the function will read as many samples per channel as will fit in buffer.
- **timeout**: The amount of time in seconds to wait for the samples to be read. Specify a negative number to wait indefinitely or **0** to return immediately with whatever samples are available.
- **buffer**: The buffer to read samples into. May be NULL if **samples_per_channel** is **0**.
- **buffer_size_samples**: The size of the buffer in samples. Each sample is a **double**.
- **samples_read_per_channel**: Returns the actual number of samples read from each channel. May be NULL if **samples_per_channel** is **0**.

int **mcc118_a_in_scan_channel_count** (uint8_t *address*)
Return the number of channels in the current analog input scan.

Return The number of channels, 0 - 8.

Parameters

- **address**: The board address (0 - 7). Board must already be opened.

int **mcc118_a_in_scan_stop** (uint8_t *address*)
Stops an analog input scan.

The scan is stopped immediately. The scan data that has been read into the scan buffer is available until *mcc118_a_in_scan_cleanup()* is called.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- **address**: The board address (0 - 7). Board must already be opened.

int **mcc118_a_in_scan_cleanup** (uint8_t *address*)
Free analog input scan resources after the scan is complete.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- **address**: The board address (0 - 7). Board must already be opened.

4.2.2 Data definitions

4.2.2.1 Trigger Modes

enum TriggerMode

Scan trigger input modes.

Values:

TRIG_RISING_EDGE = 0

Trigger on a rising edge.

TRIG_FALLING_EDGE = 1

Trigger on a falling edge.

TRIG_ACTIVE_HIGH = 2

Trigger any time the signal is high.

TRIG_ACTIVE_LOW = 3

Trigger any time the signal is low.

4.2.2.2 Scan Status Flags

STATUS_HW_OVERRUN (0x0001)

A hardware overrun occurred.

STATUS_BUFFER_OVERRUN (0x0002)

A scan buffer overrun occurred.

STATUS_TRIGGERED (0x0004)

The trigger event occurred.

STATUS_RUNNING (0x0008)

The scan is running.

4.3 MCC 134 functions and data

4.3.1 Functions

| Function | Description |
|-----------------------------------------------------|---------------------------------------------------|
| <code>mcc134_open()</code> | Open an MCC 134 for use. |
| <code>mcc134_is_open()</code> | Check if an MCC 134 is open. |
| <code>mcc134_close()</code> | Close an MCC 134. |
| <code>mcc134_serial()</code> | Read the serial number. |
| <code>mcc134_calibration_date()</code> | Read the calibration date. |
| <code>mcc134_calibration_coefficient_read()</code> | Read the calibration coefficients for a channel. |
| <code>mcc134_calibration_coefficient_write()</code> | Write the calibration coefficients for a channel. |
| <code>mcc134_a_in_num_channels()</code> | Get the number of analog input channels. |
| <code>mcc134_self_offset_correction()</code> | Clear any internal ADC offset error. |
| <code>mcc134_a_in_read()</code> | Read an analog input value. |
| <code>mcc134_tc_type_write()</code> | Write the thermocouple type for a channel. |
| <code>mcc134_tc_type_read()</code> | Read the thermocouple type for a channel. |
| <code>mcc134_t_in_read()</code> | Read a temperature input value. |
| <code>mcc134_cjc_read()</code> | Read a CJC temperature. |

int **mcc134_open** (uint8_t *address*)

Open a connection to the MCC 134 device at the specified address.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7).

int **mcc134_is_open** (uint8_t *address*)

Check if an MCC 134 is open.

Return 1 if open, 0 if not open.

Parameters

- *address*: The board address (0 - 7).

int **mcc134_close** (uint8_t *address*)

Close a connection to an MCC 134 device and free allocated resources.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7).

int **mcc134_serial** (uint8_t *address*, char * *buffer*)

Read the MCC 134 serial number.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7). Board must already be opened.
- *buffer*: Pass a user-allocated buffer pointer to receive the serial number as a string. The buffer must be at least 9 characters in length.

int **mcc134_calibration_date** (uint8_t *address*, char * *buffer*)

Read the MCC 134 calibration date.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7). Board must already be opened.
- *buffer*: Pass a user-allocated buffer pointer to receive the date as a string (format “YYYY-MM-DD”). The buffer must be at least 11 characters in length.

int **mcc134_calibration_coefficient_read** (uint8_t *address*, uint8_t *channel*, double * *slope*, double * *offset*)

Read the MCC 134 calibration coefficients for a single channel.

The coefficients are applied in the library as:

| |
|-----------------------------------------------------------------------------------------|
| $\text{calibrated_ADC_code} = (\text{raw_ADC_code} * \text{slope}) + \text{offset}$ |
|-----------------------------------------------------------------------------------------|

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The channel number (0 - 3).
- `slope`: Receives the slope.
- `offset`: Receives the offset.

int **mcc134_calibration_coefficient_write** (uint8_t *address*, uint8_t *channel*, double *slope*, double *offset*)

Temporarily write the MCC 134 calibration coefficients for a single channel.

The user can apply their own calibration coefficients by writing to these values. The values will reset to the factory values from the EEPROM whenever *mcc134_open()* is called.

The coefficients are applied in the library as:

$$\text{calibrated_ADC_code} = (\text{raw_ADC_code} * \text{slope}) + \text{offset}$$

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The channel number (0 - 3).
- `slope`: The new slope value.
- `offset`: The new offset value.

int **mcc134_a_in_num_channels** (void)

Return the number of analog input channels on the MCC 134.

Return The number of channels.

int **mcc134_self_offset_correction** (uint8_t *address*)

Clear any internal ADC offset error.

Performs an ADC self offset correction. This is automatically run when opening the board. For absolute accuracy this should be performed whenever the board temperature changes by more than 5 degrees C from the last time the offset error was cleared. The board temperature can be monitored with *mcc134_cjc_read()*. This function takes approximately 800ms to complete.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.

int **mcc134_a_in_read** (uint8_t *address*, uint8_t *channel*, uint32_t *options*, double * *value*)

Read an analog input channel.

Reads the specified channel and returns the value as voltage or ADC code. ADC code will be returned if the *OPTS_NOSCALEDATA* option is specified; otherwise, voltage will be returned.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The analog input channel number (0 - 3).
- `options`: Options bitmask (only `OPTS_NOSCALEDATA` and `OPTS_NOCALIBRATEDATA` are used)
- `value`: Receives the analog input value.

int **mcc134_tc_type_write** (uint8_t *address*, uint8_t *channel*, uint8_t *type*)

Write the thermocouple type for a channel.

Tells the MCC 134 library what thermocouple type is connected to the specified channel. This is needed for correct temperature calculations. The type is one of *tcTypes* and the board will default to all channels set to `TC_TYPE_J` when it is first opened.

Return *Result code*, `RESULT_SUCCESS` if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The analog input channel number (0 - 3).
- `type`: The thermocouple type, one of *tcTypes*.

int **mcc134_tc_type_read** (uint8_t *address*, uint8_t *channel*, uint8_t * *type*)

Read the thermocouple type for a channel.

Reads the current thermocouple type for the specified channel. The type is one of *tcTypes* and the board will default to all channels set to `TC_TYPE_J` when it is first opened.

Return *Result code*, `RESULT_SUCCESS` if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The analog input channel number (0 - 3).
- `type`: Receives the thermocouple type, one of *tcTypes*.

int **mcc134_t_in_read** (uint8_t *address*, uint8_t *channel*, double * *temperature*)

Read a temperature input channel.

Reads the specified channel and returns the value as degrees Celsius. The returned temperature can have some special values to indicate abnormal conditions:

- `OPEN_TC_VALUE` if an open thermocouple is detected on the channel.
- `OVERRRANGE_TC_VALUE` if an overrange is detected on the channel.

Return *Result code*, `RESULT_SUCCESS` if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The analog input channel number, 0 - 3.
- `temperature`: Receives the temperature value in degrees C.

int **mcc134_cjc_read** (uint8_t *address*, uint8_t *channel*, double * *cjc_temp*)

Read the cold junction compensation temperature.

Returns the temperature of the channel terminal for cold junction compensation.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7). Board must already be opened.
- *channel*: The analog input channel number, 0 - 3.
- *cjc_temp*: Receives the cold junction compensation temperature in degrees C.

4.3.2 Data definitions

OPEN_TC_VALUE (-9999.0)

Return value for an open thermocouple.

OVERRANGE_TC_VALUE (-8888.0)

Return value for thermocouple voltage outside the valid range.

4.3.2.1 Thermocouple Types

enum tcTypes

Thermocouple type constants.

Values:

TC_TYPE_J = 0

J type.

TC_TYPE_K

K type.

TC_TYPE_T

T type.

TC_TYPE_E

E type.

TC_TYPE_R

R type.

TC_TYPE_S

S type.

TC_TYPE_B

B type.

TC_TYPE_N

N type.

4.4 MCC 152 functions and data

4.4.1 Functions

| Function | Description |
|-------------------------------------------------|----------------------------------------------------------|
| <code>mcc152_open()</code> | Open an MCC 152 for use. |
| <code>mcc152_is_open()</code> | Check if an MCC 152 is open. |
| <code>mcc152_close()</code> | Close an MCC 152. |
| <code>mcc152_serial()</code> | Read the serial number. |
| <code>mcc152_a_out_num_channels()</code> | Get the number of analog output channels. |
| <code>mcc152_a_out_write()</code> | Write an analog output channel value. |
| <code>mcc152_a_out_write_all()</code> | Write all analog output channels simultaneously. |
| <code>mcc152_dio_num_channels()</code> | Get the number of digital I/O channels. |
| <code>mcc152_dio_reset()</code> | Reset the DIO to the default configuration. |
| <code>mcc152_dio_input_read()</code> | Read the DIO input(s). |
| <code>mcc152_dio_output_write()</code> | Write the DIO output(s). |
| <code>mcc152_dio_output_read()</code> | Read the DIO output state(s). |
| <code>mcc152_dio_direction_write()</code> | Set the DIO channel direction(s). |
| <code>mcc152_dio_direction_read()</code> | Read the DIO channel direction(s). |
| <code>mcc152_dio_pull_config_write()</code> | Configure the DIO pull-up / pull-down resistor(s). |
| <code>mcc152_dio_pull_config_read()</code> | Read the DIO pull-up / pull-down resistor configuration. |
| <code>mcc152_dio_pull_enable_write()</code> | Enable the DIO pull-up / pull-down resistor(s). |
| <code>mcc152_dio_pull_enable_read()</code> | Read the DIO pull-up / pull-down resistor enable value. |
| <code>mcc152_dio_input_invert_write()</code> | Configure the DIO input polarity inversion. |
| <code>mcc152_dio_input_invert_read()</code> | Read the DIO input polarity inversion configuration. |
| <code>mcc152_dio_input_latch_write()</code> | Configure the DIO input latching. |
| <code>mcc152_dio_input_latch_read()</code> | Read the DIO input latching configuration. |
| <code>mcc152_dio_output_type_write()</code> | Configure the DIO output type. |
| <code>mcc152_dio_output_type_read()</code> | Read the DIO output type configuration. |
| <code>mcc152_dio_interrupt_mask_write()</code> | Write the DIO interrupt mask. |
| <code>mcc152_dio_interrupt_mask_read()</code> | Read the DIO interrupt mask. |
| <code>mcc152_dio_interrupt_status_read()</code> | Read the DIO interrupt status. |

int **mcc152_open** (uint8_t *address*)

Open a connection to the MCC 152 device at the specified address.

Return *Result code*, `RESULT_SUCCESS` if successful.

Parameters

- *address*: The board address (0 - 7).

int **mcc152_is_open** (uint8_t *address*)

Check if an MCC 152 is open.

Return 1 if open, 0 if not open.

Parameters

- *address*: The board address (0 - 7).

int **mcc152_close** (uint8_t *address*)

Close a connection to an MCC 152 device and free allocated resources.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7).

int **mcc152_serial** (uint8_t *address*, char * *buffer*)

Read the MCC 152 serial number.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7). Board must already be opened.
- *buffer*: Pass a user-allocated buffer pointer to receive the serial number as a string. The buffer must be at least 9 characters in length.

int **mcc152_a_out_num_channels** (void)

Return the number of analog output channels on the MCC 152.

Return The number of channels.

int **mcc152_a_out_write** (uint8_t *address*, uint8_t *channel*, uint32_t *options*, double *value*)

Perform a write to an analog output channel.

Updates the analog output channel in either volts or DAC code (set the *OPTS_NOSCALEDATA* option to use DAC code.) The voltage must be 0.0-5.0 and DAC code 0.0-4095.0.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7). Board must already be opened.
- *channel*: The analog output channel number, 0 - 1.
- *options*: Options bitmask (only *OPTS_NOSCALEDATA* is used)
- *value*: The analog output value.

int **mcc152_a_out_write_all** (uint8_t *address*, uint32_t *options*, double * *values*)

Perform a write to all analog output channels simultaneously.

Update all analog output channels in either volts or DAC code (set the *OPTS_NOSCALEDATA* option to use DAC code.) The outputs will update at the same time

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7). Board must already be opened.
- *options*: Options bitmask (only *OPTS_NOSCALEDATA* is used)
- *values*: The array of analog output values; there must be at least 2 values.

int **mcc152_dio_num_channels** (void)

Return the number of digital I/O on the MCC 152.

Return The number of I/O.

int **mcc152_dio_reset** (uint8_t *address*)

Reset the DIO to the default configuration.

Resets the DIO interface to the power on defaults:

- All channels input
- Output registers set to 1
- Input inversion disabled
- No input latching
- Pull-up resistors enabled
- All interrupts disabled
- Push-pull output type

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7). Board must already be opened.

int **mcc152_dio_input_read** (uint8_t *address*, uint8_t *channel*, uint8_t * *value*)

Read the DIO input(s).

Read a single digital channel input value or all inputs at once. Will return 0 or 1 in *value* if a single channel is specified, or an 8-bit value representing all channels if *DIO_CHANNEL_ALL* is specified.

If the specified channel is configured as an output this will return the value present at the terminal.

This function reads the entire input register even if a single channel is specified, so care must be taken when latched inputs are enabled. If a latched input changes between input reads then changes back to its original value, the next input read will report the change to the first value then the following read will show the original value. If another input is read then this input change could be missed so it is best to use *DIO_CHANNEL_ALL* when using latched inputs.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7). Board must already be opened.
- *channel*: The DIO channel number, 0 - 7 or *DIO_CHANNEL_ALL* to read all channels at once.
- *value*: Receives the input value.

int **mcc152_dio_output_write** (uint8_t *address*, uint8_t *channel*, uint8_t *value*)

Write the DIO output(s).

Write a single digital channel output value or all outputs at once. Pass 0 or 1 if a single channel is specified, or an 8-bit value representing the desired output for all channels if *DIO_CHANNEL_ALL* is specified.

If the specified channel is configured as an input this will not have any effect at the terminal, but allows the output register to be loaded before configuring the channel as an output.

For example, to set channels 0 - 3 to 0 and channels 4 - 7 to 1 call:

```
mcc152_dio_output_write(address, DIO_CHANNEL_ALL, 0xF0);
```

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The DIO channel number, 0 - 7 or *DIO_CHANNEL_ALL* to write all channels at once.
- `value`: The output value(s).

int **mcc152_dio_output_read** (uint8_t *address*, uint8_t *channel*, uint8_t * *value*)

Read the DIO output register(s).

Read the value of a single digital channel output or all outputs at once. Returns 0 or 1 if a single channel is specified, or an 8-bit value representing all channels if *DIO_CHANNEL_ALL* is specified.

This function returns the value stored in the output register. It may not represent the value at the terminal if the channel is configured as input or open-drain output.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The DIO channel number, 0 - 7 or *DIO_CHANNEL_ALL* to read all channels at once.
- `value`: Receives the output value(s).

int **mcc152_dio_direction_write** (uint8_t *address*, uint8_t *channel*, uint8_t *value*)

Set the DIO channel direction(s).

Set the direction of a single digital channel or all channels at once. A 0 sets the channel to output, a 1 sets it to input. Pass 0 or 1 if a single channel is specified, or an 8-bit value representing all channels if *DIO_CHANNEL_ALL* is specified.

For example, to set channels 0 - 3 to output and channels 4 - 7 to input call:

```
mcc152_dio_direction_write(address, DIO_CHANNEL_ALL, 0xF0);
```

When switching a channel from input to output the value that is in the channel output register will be driven onto the terminal. This is set with *mcc152_dio_output_write()*.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The DIO channel number, 0 - 7 or *DIO_CHANNEL_ALL* to write all channels at once.
- `value`: The direction value(s).

int **mcc152_dio_direction_read** (uint8_t *address*, uint8_t *channel*, uint8_t * *value*)

Read the DIO channel direction(s).

Reads the direction of a single digital channel or all channels at once. A 0 indicates the channel is set to output, a 1 indicates input. Returns 0 or 1 if a single channel is specified, or an 8-bit value representing all channels if *DIO_CHANNEL_ALL* is specified.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.

- `channel`: The DIO channel number, 0 - 7 or `DIO_CHANNEL_ALL` to read all channels at once.
- `value`: Receives the direction value(s).

int `mcc152_dio_pull_config_write` (uint8_t *address*, uint8_t *channel*, uint8_t *value*)

Configure the DIO pull-up / pull-down resistor(s).

Configure the pull-up / pull-down resistor for a single digital channel or all channels at once. A 0 sets the resistor to pull-down, a 1 sets it to pull-up. Pass 0 or 1 if a single channel is specified, or an 8-bit value representing all channels if `DIO_CHANNEL_ALL` is specified.

The pull resistor is enabled or disabled with `mcc152_dio_pull_enable_write()`;

For example, to configure and enable pull-down resistors on all channels call:

```
mcc152_dio_pull_config_write(address, DIO_CHANNEL_ALL, 0x00);
mcc152_dio_pull_enable_write(address, DIO_CHANNEL_ALL, 0xFF);
```

Return *Result code*, `RESULT_SUCCESS` if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The DIO channel number, 0 - 7 or `DIO_CHANNEL_ALL` to write all channels at once.
- `value`: The pull-up/pull-down configuration.

int `mcc152_dio_pull_config_read` (uint8_t *address*, uint8_t *channel*, uint8_t * *value*)

Read the DIO pull-up / pull-down resistor configuration.

Reads the pull-up / pull-down resistor configuration for a single digital channel or all channels at once. A 0 indicates pull-down, a 1 indicates pull-up. Returns 0 or 1 if a single channel is specified, or an 8-bit value representing all channels if `DIO_CHANNEL_ALL` is specified.

Return *Result code*, `RESULT_SUCCESS` if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The DIO channel number, 0 - 7 or `DIO_CHANNEL_ALL` to read all channels at once.
- `value`: Receives the pull-up/pull-down configuration.

int `mcc152_dio_pull_enable_write` (uint8_t *address*, uint8_t *channel*, uint8_t *value*)

Enable the DIO pull-up / pull-down resistor(s).

Enable or disable the pull-up / pull-down resistor for a single digital channel or all channels at once. A 0 disables the resistor, a 1 enables it. Pass 0 or 1 if a single channel is specified, or an 8-bit value representing all channels if `DIO_CHANNEL_ALL` is specified.

The pull resistor is configured as pull-up or pull-down with `mcc152_dio_pull_config_write()`;

For example, to configure and enable pull-down resistors on all channels call:

```
mcc152_dio_pull_config_write(address, DIO_CHANNEL_ALL, 0x00);
mcc152_dio_pull_enable_write(address, DIO_CHANNEL_ALL, 0xFF);
```

Return *Result code*, `RESULT_SUCCESS` if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The DIO channel number, 0 - 7 or `DIO_CHANNEL_ALL` to write all channels at once.
- `value`: The pull enable value.

int **mcc152_dio_pull_enable_read** (uint8_t *address*, uint8_t *channel*, uint8_t * *value*)

Read the DIO pull-up / pull-down resistor enable value.

Reads the pull-up / pull-down resistor enable value for a single digital channel or all channels at once. A 0 indicates the resistor is disabled, a 1 indicates enabled. Returns 0 or 1 if a single channel is specified, or an 8-bit value representing all channels if `DIO_CHANNEL_ALL` is specified.

Return *Result code*, `RESULT_SUCCESS` if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The DIO channel number, 0 - 7 or `DIO_CHANNEL_ALL` to read all channels at once.
- `value`: Receives the pull-up/pull-down enable value.

int **mcc152_dio_input_invert_write** (uint8_t *address*, uint8_t *channel*, uint8_t *value*)

Configure the DIO input polarity inversion.

Configure input polarity inversion for a single digital channel or all channels at once. A 0 sets the input to normal polarity, a 1 sets it to inverted. Pass 0 or 1 if a single channel is specified, or an 8-bit value representing all channels if `DIO_CHANNEL_ALL` is specified.

Return *Result code*, `RESULT_SUCCESS` if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The DIO channel number, 0 - 7 or `DIO_CHANNEL_ALL` to write all channels at once.
- `value`: The polarity inversion value.

int **mcc152_dio_input_invert_read** (uint8_t *address*, uint8_t *channel*, uint8_t * *value*)

Read the DIO input polarity inversion configuration.

Reads the current input polarity inversion configuration for a single digital channel or all channels at once. A 0 represents normal polarity, 1 represents inverted. Returns 0 or 1 if a single channel is specified, or an 8-bit value representing all channels in a single value if `DIO_CHANNEL_ALL` is specified.

Return *Result code*, `RESULT_SUCCESS` if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The DIO channel number, 0 - 7 or `DIO_CHANNEL_ALL` to read all channels at once.
- `value`: Receives the polarity inversion value.

int **mcc152_dio_input_latch_write** (uint8_t *address*, uint8_t *channel*, uint8_t *value*)

Configure the DIO input latching.

Configure input latching for a single digital channel or all channels at once. When input latching is set to 0 the corresponding input state is not latched, so reads show the current status of the input. A state change in the

corresponding input generates an interrupt (if it is not masked). A read of the input clears the interrupt. If the input goes back to its initial logic state before the input is read, then the interrupt is cleared.

When it is set to 1, the corresponding input state is latched. A change of state of the input generates an interrupt and the input logic value is loaded into the input port register. A read of the input will clear the interrupt. If the input returns to its initial logic state before the input is read, then the interrupt is not cleared and the input register keeps the logic value that initiated the interrupt. The next read of the input will show the initial state.

If the input terminal is changed from latched to non-latched input, a read from the input reflects the current terminal logic level. If the input terminal is changed from non-latched to latched input, the read from the input represents the latched logic level.

Pass 0 or 1 if a single channel is specified, or an 8-bit value representing all channels if *DIO_CHANNEL_ALL* is specified.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7). Board must already be opened.
- *channel*: The DIO channel number, 0 - 7 or *DIO_CHANNEL_ALL* to write all channels at once.
- *value*: The input latch value.

int **mcc152_dio_input_latch_read** (uint8_t *address*, uint8_t *channel*, uint8_t * *value*)

Read the DIO input latching configuration.

Read the input latching configuration for a single digital channel or all channels at once. Returns 0 or 1 if a single channel is specified, or an 8-bit value representing all channels in a single value if *DIO_CHANNEL_ALL* is specified.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7). Board must already be opened.
- *channel*: The DIO channel number, 0 - 7 or *DIO_CHANNEL_ALL* to read all channels at once.
- *value*: Receives the input latch value.

int **mcc152_dio_output_type_write** (uint8_t *address*, uint8_t *value*)

Configure the DIO output type.

Configure digital outputs as push-pull or open-drain. This is a single value that affects all of the digital outputs on the MCC 152. Pass a 0 for push-pull or a 1 for open-drain.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- *address*: The board address (0 - 7). Board must already be opened.
- *value*: The output type value, 0 or 1.

int **mcc152_dio_output_type_read** (uint8_t *address*, uint8_t * *value*)

Read the DIO output type configuration.

Read the digital output type configuration. Returns 0 for push-pull, 1 for open-drain.

Return *Result code*, *RESULT_SUCCESS* if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `value`: Receives the output type value.

int **mcc152_dio_interrupt_mask_write** (uint8_t *address*, uint8_t *channel*, uint8_t *value*)

Write the DIO interrupt mask.

Configures the interrupt mask. A 1 disables (masks) the interrupt for the specified channel, a 0 enables it. Pass 0 or 1 if a single channel is specified, or an 8-bit value representing all channels if [DIO_CHANNEL_ALL](#) is specified.

The current interrupt state may be read with [hat_interrupt_active\(\)](#). A user program may wait for the interrupt to become active with [hat_wait_for_interrupt\(\)](#). This allows the user to wait for a change on one or more inputs without constantly reading the inputs. The interrupt is cleared by reading the input(s) with [mcc152_dio_input_read\(\)](#). Multiple MCC 152s will share a single interrupt signal, so the source of the interrupt may be determined by reading the interrupt status of each board with `mcc152_dio_interrupt_status()` and all active interrupt sources must be cleared before the interrupt will become inactive.

Return *Result code*, [RESULT_SUCCESS](#) if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The DIO channel number, 0 - 7 or [DIO_CHANNEL_ALL](#) to write all channels at once.
- `value`: The interrupt mask value.

int **mcc152_dio_interrupt_mask_read** (uint8_t *address*, uint8_t *channel*, uint8_t * *value*)

Read the DIO interrupt mask.

Reads the interrupt mask for a single digital channel or all channels at once. A 0 indicates the interrupt is enabled, 1 indicates interrupt is disabled. Returns 0 or 1 if a single channel is specified, or an 8-bit value representing all channels if [DIO_CHANNEL_ALL](#) is specified.

Return *Result code*, [RESULT_SUCCESS](#) if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The DIO channel number, 0 - 7 or [DIO_CHANNEL_ALL](#) to read all channels at once.
- `value`: Receives the interrupt mask value.

int **mcc152_dio_interrupt_status_read** (uint8_t *address*, uint8_t *channel*, uint8_t * *value*)

Read the DIO interrupt status.

Reads the interrupt status for a single digital channel or all channels at once. A 0 indicates the channel is not the source of the interrupt, 1 indicates the channel was a source of the interrupt. Returns 0 or 1 if a single channel is specified, or an 8-bit value representing all channels if [DIO_CHANNEL_ALL](#) is specified.

Return *Result code*, [RESULT_SUCCESS](#) if successful.

Parameters

- `address`: The board address (0 - 7). Board must already be opened.
- `channel`: The DIO channel number, 0 - 7 or [DIO_CHANNEL_ALL](#) to read all channels at once.
- `value`: Receives the interrupt status value.

4.4.2 Data definitions

DIO_CHANNEL_ALL (0xFF)

Write or read a value for all channels.

PYTHON LIBRARY REFERENCE

The Python library is organized as a global method for listing the HAT boards attached to your system, and board-specific classes to provide full functionality for each type of board. The Python package is named *daqhats*.

5.1 Global methods and data

5.1.1 Methods

| Method | Description |
|-------------------------|-------------------------------------------|
| <code>hat_list()</code> | Return a list of detected MCC HAT boards. |

`daqhats.hat_list (filter_by_id=0)`

Return a list of detected MCC HAT boards.

Scans certain locations for information from the HAT EEPROMs. Verifies the contents are valid HAT EEPROM contents and returns a list of dictionaries containing information on the HAT. Info will only be returned for MCC HATs. The EEPROM contents are stored in `/etc/mcc/hats` when using the `daqhats_read_eeproms` tool, or in `/proc/device-tree` in the case of a single HAT at address 0.

Parameters `filter_by_id` (*int*) – If this is `HatIDs.ANY` return all MCC HATs found. Otherwise, return only HATs with ID matching this value.

Returns

A list of dictionaries, the number of elements match the number of HATs found. Each dictionary will contain the following keys

address (*int*): device address

id (*int*): device product ID, identifies the type of MCC HAT

version (*int*): device hardware version

product_name (*str*): device product name

Return type `list`

5.1.2 Data

5.1.2.1 Hat IDs

```
class daqhats.HatIDs
    Known MCC HAT IDs.

    ANY = 0
        Match any MCC ID in hat_list()

    MCC_118 = 322
        MCC 118 ID

    MCC_134 = 323
        MCC 134 ID
```

5.1.2.2 Trigger modes

```
class daqhats.TriggerModes
    Scan trigger input modes.

    RISING_EDGE = 0
        Trigger on a rising edge.

    FALLING_EDGE = 1
        Trigger on a falling edge.

    ACTIVE_HIGH = 2
        Trigger any time the signal is high

    ACTIVE_LOW = 3
        Trigger any time the signal is low.
```

5.1.3 HatError class

```
exception daqhats.HatError(address, value)
    Exceptions raised for MCC HAT specific errors.
```

Parameters

- **address** (*int*) – the address of the board that caused the exception.
- **value** (*str*) – the exception description.

5.2 MCC 118 class

5.2.1 Methods

```
class daqhats.mcc118(address=0)
    The class for an MCC 118 board.
```

Parameters **address** (*int*) – board address, must be 0-7.

Raises *HatError* – the board did not respond or was of an incorrect type

Methods

| Method | Description |
|-----------------------------------------------------|----------------------------------------------------------|
| <code>mcc118.blink_led()</code> | Blink the MCC 118 LED. |
| <code>mcc118.firmware_version()</code> | Get the firmware version. |
| <code>mcc118.address()</code> | Read the board's address. |
| <code>mcc118.serial()</code> | Read the serial number. |
| <code>mcc118.calibration_date()</code> | Read the calibration date. |
| <code>mcc118.calibration_coefficient_read()</code> | Read the calibration coefficients for a channel. |
| <code>mcc118.calibration_coefficient_write()</code> | Write the calibration coefficients for a channel. |
| <code>mcc118.a_in_num_channels()</code> | Get the number of analog input channels. |
| <code>mcc118.a_in_read()</code> | Read an analog input channel. |
| <code>mcc118.trigger_mode()</code> | Set the external trigger input mode. |
| <code>mcc118.a_in_scan_actual_rate()</code> | Read the actual sample rate for a requested sample rate. |
| <code>mcc118.a_in_scan_start()</code> | Start a hardware-paced analog input scan. |
| <code>mcc118.a_in_scan_buffer_size()</code> | Read the size of the internal scan data buffer. |
| <code>mcc118.a_in_scan_read()</code> | Read scan status / data (list). |
| <code>mcc118.a_in_scan_read_numpy()</code> | Read scan status / data (NumPy array). |
| <code>mcc118.a_in_scan_channel_count()</code> | Get the number of channels in the current scan. |
| <code>mcc118.a_in_scan_stop()</code> | Stop the scan. |
| <code>mcc118.a_in_scan_cleanup()</code> | Free scan resources. |

firmware_version()

Read the board firmware and bootloader versions.

Returns

versions containing the following keys

version (string): The firmware version, i.e “1.03”.

bootloader_version (string): The bootloader version, i.e “1.01”.

Return type dictionary

Raises *HatError* – the board is not initialized, does not respond, or responds incorrectly.

serial()

Read the serial number.

Returns The serial number.

Return type string

Raises *HatError* – the board is not initialized, does not respond, or responds incorrectly.

blink_led(count)

Blink the MCC 118 LED.

Parameters **count** (*int*) – The number of times to blink (max 255).

Raises *HatError* – the board is not initialized, does not respond, or responds incorrectly.

calibration_date()

Read the calibration date.

Returns The calibration date in the format “YYYY-MM-DD”.

Return type string

Raises *HatError* – the board is not initialized, does not respond, or responds incorrectly.

calibration_coefficient_read (*channel*)

Read the calibration coefficients for a single channel.

The coefficients are applied in the library as:

```
calibrated_ADC_code = (raw_ADC_code * slope) + offset
```

Returns

coefficients containing the following keys

slope (float): The slope.

offset (float): The offset.

Return type dictionary

Raises *HatError* – the board is not initialized, does not respond, or responds incorrectly.

calibration_coefficient_write (*channel*, *slope*, *offset*)

Temporarily write the calibration coefficients for a single channel.

The user can apply their own calibration coefficients by writing to these values. The values will reset to the factory values from the EEPROM whenever the class is initialized. This function will fail and raise a *HatError* exception if a scan is running when it is called.

The coefficients are applied in the library as:

```
calibrated_ADC_code = (raw_ADC_code * slope) + offset
```

Parameters

- **slope** (*float*) – The new slope value.
- **offset** (*float*) – The new offset value.

Raises *HatError* – the board is not initialized, does not respond, or responds incorrectly.

trigger_mode (*mode*)

Set the external trigger input mode.

The available modes are:

- *TriggerModes.RISING_EDGE*: Trigger when the TRIG input transitions from low to high.
- *TriggerModes.FALLING_EDGE*: Trigger when the TRIG input transitions from high to low.
- *TriggerModes.ACTIVE_HIGH*: Trigger when the TRIG input is high.
- *TriggerModes.ACTIVE_LOW*: Trigger when the TRIG input is low.

Parameters **mode** (*TriggerModes*) – The trigger mode.

Raises *HatError* – the board is not initialized, does not respond, or responds incorrectly.

static a_in_num_channels()

Return the number of analog input channels.

Returns the number of channels.

Return type int

a_in_read(channel, scaled=True, calibrated=True)

Perform a single reading of an analog input channel and return the value.

Parameters

- **channel** (*int*) – The analog input channel number, 0-7.
- **scaled** (*bool*) – True to return voltage, False to return ADC code.
- **calibrated** (*bool*) – True to apply calibration to the value, False to return uncalibrated value.

Returns the read value

Return type float

Raises

- *HatError* – the board is not initialized, does not respond, or responds incorrectly.
- *ValueError* – the channel number is invalid.

a_in_scan_actual_rate(channel_count, sample_rate_per_channel)

Read the actual sample rate per channel for a requested sample rate.

The internal scan clock is generated from a 16 MHz clock source so only discrete frequency steps can be achieved. This function will return the actual rate for a requested channel count and rate setting.

This function does not perform any actions with a board, it simply calculates the rate.

Parameters

- **channel_count** (*int*) – The number of channels in the scan, 1-8.
- **sample_rate_per_channel** (*float*) – The desired per-channel rate of the internal sampling clock, max 100,000.0.

Returns the actual sample rate

Return type float

Raises *ValueError* – a scan argument is invalid.

a_in_scan_start(channel_mask, samples_per_channel, sample_rate_per_channel, continuous=False, external_clock=False, external_trigger=False, scaled=True, calibrated=True)

Start a hardware-paced analog input channel scan.

The scan runs as a separate thread from the user's code. This function will allocate a scan buffer and start the thread that reads data from the device into that buffer. The user reads the data from the scan buffer and the scan status using the [a_in_scan_read\(\)](#) function. [a_in_scan_stop\(\)](#) is used to stop a continuous scan, or to stop a finite scan before it completes. The user must call [a_in_scan_cleanup\(\)](#) after the scan has finished and all desired data has been read; this frees all resources from the scan and allows additional scans to be performed.

The scan buffer size will be allocated as follows:

Finite mode: Total number of samples in the scan.

Continuous mode: Either **samples_per_channel** or the value in the table below, whichever is greater.

| Sample Rate | Buffer Size (per channel) |
|---------------|---------------------------|
| Not specified | 10 kS |
| 0-100 S/s | 1 kS |
| 100-10k S/s | 10 kS |
| 10k-100k S/s | 100 kS |

Specifying a very large value for `samples_per_channel` could use too much of the Raspberry Pi memory. If the memory allocation fails, the function will raise a `HatError` with this description. The allocation could succeed, but the lack of free memory could cause other problems in the Raspberry Pi. If you need to acquire a high number of samples then it is better to run the scan in continuous mode and stop it when you have acquired the desired amount of data. If a scan is already running this function will raise a `HatError`.

Parameters

- **channel_mask** (*int*) – A bit mask of the desired channels (0x01 - 0xFF).
- **samples_per_channel** (*int*) – The number of samples to acquire per channel.
- **sample_rate_per_channel** (*float*) – The per-channel rate of the internal sampling clock, or the expected maximum rate of an external sampling clock, max 100,000.0.
- **continuous** (*bool*) – False for a finite scan, True for a scan that runs until stopped by the user.
- **external_clock** (*bool*) – False to use the internal sampling clock, True to use an external clock on the CLK pin.
- **external_trigger** (*bool*) – False to start the scan immediately, True to start the scan when the external trigger conditions (set with `trigger_mode()`) are met on the TRIG pin.
- **scaled** (*bool*) – True to return voltage, False to return A/D code.
- **calibrated** (*bool*) – True to apply calibration to the value, False to return uncalibrated value.

Raises

- `HatError` – a scan is already running; memory could not be allocated; the board is not initialized, does not respond, or responds incorrectly.
- `ValueError` – a scan argument is invalid.

Examples

```
>>> a_in_scan_start(channel_mask = 0x05, samples_per_channel = 1000, sample_
↳ rate_per_channel = 10000)
```

This will include channels 0 and 2 in the scan. 1000 samples will be acquired per channel, resulting in 2000 samples being read (`samples_per_channel * number of channels`). The sample rate per channel is 10,000 Hz, so the ADC will convert at a frequency of 20,000 Hz (`sample_rate_per_channel * number of channels`). The scan will start immediately.

`a_in_scan_buffer_size()`

Read the internal scan data buffer size.

An internal data buffer is allocated for the scan when `a_in_scan_start()` is called. This function returns the total size of that buffer in samples.

Returns the buffer size in samples

Return type int

Raises `HatError` – the board is not initialized or no scan buffer is allocated (a scan is not running).

`a_in_scan_read` (*samples_per_channel*, *timeout*)

Read scan status and data (as a list).

The analog input scan is started with `a_in_scan_start()` and runs in the background. This function reads the status of that background scan and optionally reads sampled data from the scan buffer.

Parameters

- **`samples_per_channel`** (*int*) – The number of samples per channel to read from the scan buffer. Specify -1 to read all available samples or 0 to only read the scan status and return no data.
- **`timeout`** (*float*) – The amount of time in seconds to wait for the samples to be read. Specify a negative number to wait indefinitely, or 0 to return immediately with the samples that are already in the scan buffer. If the timeout is met and the specified number of samples have not been read, then the function will return with the amount that has been read and the timeout status set.

Returns

a dictionary containing the following keys:

`running` (bool): True if the scan is running, False if it has stopped or completed.

`hardware_overrun` (bool): True if the hardware could not acquire and unload samples fast enough and data was lost.

`buffer_overrun` (bool): True if the background scan buffer was not read fast enough and data was lost.

`triggered` (bool): True if the trigger conditions have been met and data acquisition started.

`timeout` (bool): True if the timeout time expired before the specified number of samples were read.

`data` (list of float): The data that was read from the scan buffer.

Return type dictionary

Raises `HatError` – the board is not initialized, does not respond, or responds incorrectly.

`a_in_scan_read_numpy` (*samples_per_channel*, *timeout*)

Read scan status and data (as a NumPy array).

This function is similar to `a_in_scan_read()` except that the `data` key in the returned dictionary is a NumPy array of float64 values and may be used directly with NumPy functions.

Parameters

- **`samples_per_channel`** (*int*) – The number of samples per channel to read from the scan buffer. Specify -1 to read all available samples or 0 to only read the scan status and return no data.
- **`timeout`** (*float*) – The amount of time in seconds to wait for the samples to be read. Specify a negative number to wait indefinitely, or 0 to return immediately with the samples that are already in the scan buffer. If the timeout is met and the specified number of samples have not been read, then the function will return with the amount that has been read and the timeout status set.

Returns

a dictionary containing the following keys:

running (bool): True if the scan is running, False if it has stopped or completed.

hardware_overflow (bool): True if the hardware could not acquire and unload samples fast enough and data was lost.

buffer_overflow (bool): True if the background scan buffer was not read fast enough and data was lost.

triggered (bool): True if the trigger conditions have been met and data acquisition started.

timeout (bool): True if the timeout time expired before the specified number of samples were read.

data (NumPy array of float64): The data that was read from the scan buffer.

Return type dictionary

Raises `HatError` – the board is not initialized, does not respond, or responds incorrectly.

a_in_scan_channel_count ()

Read the number of channels in the current analog input scan.

Returns the number of channels (0 if no scan is running, 1-8 otherwise)

Return type int

Raises `HatError` – the board is not initialized, does not respond, or responds incorrectly.

a_in_scan_stop ()

Stops an analog input scan.

The scan is stopped immediately. The scan data that has been read into the scan buffer is available until `a_in_scan_cleanup()` is called.

Raises `HatError` – the board is not initialized, does not respond, or responds incorrectly.

a_in_scan_cleanup ()

Free analog input scan resources after the scan is complete.

This will free the scan buffer and other resources used by the background scan and make it possible to start another scan with `a_in_scan_start()`

Raises `HatError` – the board is not initialized, does not respond, or responds incorrectly.

address ()

Return the device address.

5.3 MCC 134 class

5.3.1 Methods

class `daqhats.mcc134 (address=0)`

The class for an MCC 134 board.

Parameters `address` (*int*) – board address, must be 0-7.

Raises `HatError` – the board did not respond or was of an incorrect type

Methods

| Method | Description |
|-----------------------------------------------------|---------------------------------------------------|
| <code>mcc134.address()</code> | Read the board's address. |
| <code>mcc134.serial()</code> | Read the serial number. |
| <code>mcc134.calibration_date()</code> | Read the calibration date. |
| <code>mcc134.calibration_coefficient_read()</code> | Read the calibration coefficients for a channel. |
| <code>mcc134.calibration_coefficient_write()</code> | Write the calibration coefficients for a channel. |
| <code>mcc134.a_in_num_channels()</code> | Get the number of analog input channels. |
| <code>mcc134.self_offset_correction()</code> | Clear any internal ADC offset error. |
| <code>mcc134.a_in_read()</code> | Read an analog input channel. |
| <code>mcc134.tc_type_read()</code> | Read the thermocouple type for a channel. |
| <code>mcc134.tc_type_write()</code> | Write the thermocouple type for a channel. |
| <code>mcc134.t_in_read()</code> | Read a temperature input channel. |
| <code>mcc134.cjc_read()</code> | Read a CJC temperature |

OPEN_TC_VALUE = -9999.0

Return value for an open thermocouple.

OVERRANGE_TC_VALUE = -8888.0

Return value for thermocouple voltage outside the valid range.

serial()

Read the serial number.

Returns The serial number.

Return type string

Raises *HatError* – the board is not initialized, does not respond, or responds incorrectly.

calibration_date()

Read the calibration date.

Returns The calibration date in the format “YYYY-MM-DD”.

Return type string

Raises *HatError* – the board is not initialized, does not respond, or responds incorrectly.

calibration_coefficient_read(channel)

Read the calibration coefficients for a single channel.

The coefficients are applied in the library as:

```
calibrated_ADC_code = (raw_ADC_code * slope) + offset
```

Returns

coefficients containing the following keys

slope (float): The slope.

offset (float): The offset.

Return type dictionary

Raises *HatError* – the board is not initialized, does not respond, or responds incorrectly.

calibration_coefficient_write (*channel*, *slope*, *offset*)

Temporarily write the calibration coefficients for a single channel.

The user can apply their own calibration coefficients by writing to these values. The values will reset to the factory values from the EEPROM whenever the class is initialized.

The coefficients are applied in the library as:

```
calibrated_ADC_code = (raw_ADC_code * slope) + offset
```

Parameters

- **slope** (*float*) – The new slope value.
- **offset** (*float*) – The new offset value.

Raises *HatError* – the board is not initialized, does not respond, or responds incorrectly.

static a_in_num_channels ()

Return the number of analog input channels.

Returns the number of channels.

Return type int

self_offset_correction ()

Clear any internal ADC offset error.

Performs an ADC self offset correction. This is automatically called when the board is opened. For absolute accuracy this should be performed whenever the board temperature changes by more than 5 degrees C from the last time the offset error was cleared. The board temperature can be monitored with the *cjc_read()* method. The calibration takes approximately 800ms to complete.

Raises *HatError* – the board is not initialized, does not respond, or responds incorrectly.

a_in_read (*channel*, *scaled=True*, *calibrated=True*)

Read an analog input channel and return the value.

Parameters

- **channel** (*int*) – The analog input channel number, 0-3.
- **scaled** (*bool*) – True to return voltage, False to return ADC code.
- **calibrated** (*bool*) – True to apply calibration to the value, False to return uncalibrated value.

Returns the read value

Return type float

Raises

- *HatError* – the board is not initialized, does not respond, or responds incorrectly.
- *ValueError* – the channel number is invalid.

tc_type_read (*channel*)

Read the thermocouple type for a channel.

Reads the current thermocouple type for the specified channel. The type is one of *tcTypes* and the board will default to all channels set to *tcTypes.TYPE_J* when it is first opened.

Parameters `channel` (*int*) – The analog input channel number, 0-3.

Returns *int*: The thermocouple type.

Raises `HatError` – the board is not initialized, does not respond, or responds incorrectly.

`tc_type_write` (*channel*, *type*)

Write the thermocouple type for a channel.

Tells the MCC 134 library what thermocouple type is connected to the specified channel. This is needed for correct temperature calculations. The type is one of `tcTypes` and the board will default to all channels set to `tcTypes.TYPE_J` when it is first opened.

Parameters

- **`channel`** (*int*) – The analog input channel number, 0-3.
- **`type`** (*tcTypes*) – The thermocouple type.

Raises `HatError` – the board is not initialized, does not respond, or responds incorrectly.

`address` ()

Return the device address.

`t_in_read` (*channel*)

Read a thermocouple input channel.

Returns the value as degrees Celsius. The temperature value can have two special values:

- `mcc134.OPEN_TC_VALUE` if an open thermocouple is detected
- `mcc134.OVERRANGE_TC_VALUE` if a value outside valid thermocouple voltage is detected

Parameters `channel` (*int*) – The analog input channel number, 0-3.

Returns The thermocouple temperature.

Return type *float*

Raises

- `HatError` – the board is not initialized, does not respond, or responds incorrectly.
- `ValueError` – the channel number is invalid.

`cjc_read` (*channel*)

Read a cold junction compensation temperature.

Returns the temperature of the specified terminal in degrees Celsius.

Parameters `channel` (*int*) – The analog input channel number, 0-3.

Returns The CJC temperature.

Return type *float*

Raises

- `HatError` – the board is not initialized, does not respond, or responds incorrectly.
- `ValueError` – the channel number is invalid.

5.3.2 Data

5.3.2.1 Thermocouple types

class `daqhats.tcTypes`

Thermocouple types.

TYPE_J = 0

Type J

TYPE_K = 1

Type K

TYPE_T = 2

Type T

TYPE_E = 3

Type E

TYPE_R = 4

Type R

TYPE_S = 5

Type S

TYPE_B = 6

Type B

TYPE_N = 7

Type N

A

ACTIVE_HIGH (daqhats.TriggerModes attribute), 42
 ACTIVE_LOW (daqhats.TriggerModes attribute), 42
 address() (daqhats.mcc118 method), 48
 address() (daqhats.mcc134 method), 51
 ANY (daqhats.HatIDs attribute), 42

B

blink_led() (daqhats.mcc118 method), 43

C

calibration_coefficient_read() (daqhats.mcc118 method), 44
 calibration_coefficient_read() (daqhats.mcc134 method), 49
 calibration_coefficient_write() (daqhats.mcc118 method), 44
 calibration_coefficient_write() (daqhats.mcc134 method), 50
 calibration_date() (daqhats.mcc118 method), 43
 calibration_date() (daqhats.mcc134 method), 49
 cjc_read() (daqhats.mcc134 method), 51

F

FALLING_EDGE (daqhats.TriggerModes attribute), 42
 firmware_version() (daqhats.mcc118 method), 43

H

hat_interrupt_active (C function), 18

hat_list (C function), 17
 hat_list() (in module daqhats), 41
 hat_wait_for_interrupt (C function), 18
 HatError, 42
 HatIDs (class in daqhats), 42

M

mcc118 (class in daqhats), 42
 mcc118_a_in_num_channels (C function), 22
 mcc118_a_in_read (C function), 22
 mcc118_a_in_scan_actual_rate (C function), 23
 mcc118_a_in_scan_buffer_size (C function), 24
 mcc118_a_in_scan_channel_count (C function), 25
 mcc118_a_in_scan_cleanup (C function), 25
 mcc118_a_in_scan_read (C function), 24
 mcc118_a_in_scan_start (C function), 23
 mcc118_a_in_scan_stop (C function), 25
 mcc118_blink_led (C function), 21
 mcc118_calibration_coefficient_read (C function), 21
 mcc118_calibration_coefficient_write (C function), 22
 mcc118_calibration_date (C function), 21
 mcc118_close (C function), 20
 mcc118_firmware_version (C function), 21
 mcc118_is_open (C function), 20
 mcc118_open (C function), 20
 mcc118_serial (C function), 21
 mcc118_trigger_mode (C function), 23
 mcc134 (class in daqhats), 48
 mcc134_a_in_num_channels (C function), 28
 mcc134_a_in_read (C function), 28
 mcc134_calibration_coefficient_read (C function), 27
 mcc134_calibration_coefficient_write (C function), 28
 mcc134_calibration_date (C function), 27
 mcc134_cjc_read (C function), 29
 mcc134_close (C function), 27
 mcc134_is_open (C function), 27
 mcc134_open (C function), 27
 mcc134_self_offset_correction (C function), 28
 mcc134_serial (C function), 27
 mcc134_t_in_read (C function), 29
 mcc134_tc_type_read (C function), 29
 mcc134_tc_type_write (C function), 29

mcc152_a_out_num_channels (C function), 32
mcc152_a_out_write (C function), 32
mcc152_a_out_write_all (C function), 32
mcc152_close (C function), 31
mcc152_dio_direction_read (C function), 34
mcc152_dio_direction_write (C function), 34
mcc152_dio_input_invert_read (C function), 36
mcc152_dio_input_invert_write (C function), 36
mcc152_dio_input_latch_read (C function), 37
mcc152_dio_input_latch_write (C function), 36
mcc152_dio_input_read (C function), 33
mcc152_dio_interrupt_mask_read (C function), 38
mcc152_dio_interrupt_mask_write (C function), 38
mcc152_dio_interrupt_status_read (C function), 38
mcc152_dio_num_channels (C function), 32
mcc152_dio_output_read (C function), 34
mcc152_dio_output_type_read (C function), 37
mcc152_dio_output_type_write (C function), 37
mcc152_dio_output_write (C function), 33
mcc152_dio_pull_config_read (C function), 35
mcc152_dio_pull_config_write (C function), 35
mcc152_dio_pull_enable_read (C function), 36
mcc152_dio_pull_enable_write (C function), 35
mcc152_dio_reset (C function), 32
mcc152_is_open (C function), 31
mcc152_open (C function), 31
mcc152_serial (C function), 32
MCC_118 (daqhats.HatIDs attribute), 42
MCC_134 (daqhats.HatIDs attribute), 42

O

OPEN_TC_VALUE (daqhats.mcc134 attribute), 49
OVERRANGE_TC_VALUE (daqhats.mcc134 attribute),
49

R

RISING_EDGE (daqhats.TriggerModes attribute), 42

S

self_offset_correction() (daqhats.mcc134 method), 50
serial() (daqhats.mcc118 method), 43
serial() (daqhats.mcc134 method), 49

T

t_in_read() (daqhats.mcc134 method), 51
tc_type_read() (daqhats.mcc134 method), 50
tc_type_write() (daqhats.mcc134 method), 51
tcTypes (class in daqhats), 52
trigger_mode() (daqhats.mcc118 method), 44
TriggerModes (class in daqhats), 42
TYPE_B (daqhats.tcTypes attribute), 52
TYPE_E (daqhats.tcTypes attribute), 52
TYPE_J (daqhats.tcTypes attribute), 52

TYPE_K (daqhats.tcTypes attribute), 52
TYPE_N (daqhats.tcTypes attribute), 52
TYPE_R (daqhats.tcTypes attribute), 52
TYPE_S (daqhats.tcTypes attribute), 52
TYPE_T (daqhats.tcTypes attribute), 52